



## **BTW 5.5.0.5800**

### **Release Notes**

December 15, 2008

---

*Confidential and Proprietary Information*

---

© Broadcom Corp., 2008, All rights reserved.  
Printed in United States of America.  
16340 West Bernardo Drive  
San Diego, CA 92127  
Phone: (858) 385-8800  
Fax: (858) 385-8810

---

## LICENSED SOFTWARE

---

©200x Broadcom Corporation

This program is the proprietary software of Broadcom Corporation and/or its licensors, and may only be used, duplicated, modified or distributed pursuant to the terms and conditions of a separate, written license agreement executed between you and Broadcom (an "Authorized License"). Except as set forth in an Authorized License, Broadcom grants no license (express or implied), right to use, or waiver of any kind with respect to the Software, and Broadcom expressly reserves all rights in and to the Software and all intellectual property rights therein. IF YOU HAVE NO AUTHORIZED LICENSE, THEN YOU HAVE NO RIGHT TO USE THIS SOFTWARE IN ANY WAY, AND SHOULD IMMEDIATELY NOTIFY BROADCOM AND DISCONTINUE ALL USE OF THE SOFTWARE.

Except as expressly set forth in the Authorized License,

1. This program, including its structure, sequence and organization, constitutes the valuable trade secrets of Broadcom, and you shall use all reasonable efforts to protect the confidentiality thereof, and to use this information only in connection with your use of Broadcom integrated circuit products.
2. TO THE MAXIMUM EXTENT PERMITTED BY LAW, THE SOFTWARE IS PROVIDED "AS IS" AND WITH ALL FAULTS AND BROADCOM MAKES NO PROMISES, REPRESENTATIONS OR WARRANTIES, EITHER EXPRESS, IMPLIED, STATUTORY, OR OTHERWISE, WITH RESPECT TO THE SOFTWARE. BROADCOM SPECIFICALLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES OF TITLE, MERCHANTABILITY, NONINFRINGEMENT, FITNESS FOR A PARTICULAR PURPOSE, LACK OF VIRUSES, ACCURACY OR COMPLETENESS, QUIET ENJOYMENT, QUIET POSSESSION OR CORRESPONDENCE TO DESCRIPTION. YOU ASSUME THE ENTIRE RISK ARISING OUT OF USE OR PERFORMANCE OF THE SOFTWARE.
3. TO THE MAXIMUM EXTENT PERMITTED BY LAW, IN NO EVENT SHALL BROADCOM OR ITS LICENSORS BE LIABLE FOR (i) CONSEQUENTIAL, INCIDENTAL, SPECIAL, INDIRECT, OR EXEMPLARY DAMAGES WHATSOEVER ARISING OUT OF OR IN ANY WAY RELATING TO YOUR USE OF OR INABILITY TO USE THE SOFTWARE EVEN IF BROADCOM HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES; OR (ii) ANY AMOUNT IN EXCESS OF THE AMOUNT ACTUALLY PAID FOR THE SOFTWARE ITSELF OR U.S. \$1, WHICHEVER IS GREATER. THESE LIMITATIONS SHALL APPLY NOTWITHSTANDING ANY FAILURE OF ESSENTIAL PURPOSE OF ANY LIMITED REMEDY.

---

## INTRODUCTION

---

---

## CUSTOMER SUPPORT PORTAL (CSP)

---

Customers can submit enhancements, changes and/or defects against releases of software or firmware via the Broadcom Customer Support Portal (CSP). CSP cases are replicated into the Broadcom Bluetooth engineering change management database for review by the engineering community and change control boards.

If your project or program is not listed inside the CSP please contact your Broadcom representative whom can configure the CSP system for use with your unique needs.

To start using the CSP please visit <http://support.broadcom.com>.

## Installation Command Line Options

To install BTW from command line prompt or from a batch file, use the following command line options:

Setup.exe [/qn | /qb | /qr] [/nw] [/nodfu] [/L<LangId>] [/ru] [/ri]

/qn - Silent install without any UI and user interaction

/qb - Silent install with basic UI with progress dialog without any user interaction

/qr - Silent install with full UI without any user interaction

/nw- Setup.exe does not wait for BTW install to complete, exits after invoking MSI install.

/nodfu- Do not execute DFU during BTW install (even if configured for DFU in SvcPack.ini file)

/noinf - Do not install USB inf file, bcbtums\*.inf for Vista and btwusb.inf for XP. (Newly added since 5.5.0.900 and 6.1.0.2800)

/L -Installation language

<LangId> can be one of the following

1033: English

1046: Portuguese (Brazilian)

1028: Chinese Tradition

2052: Chinese Simplified

1030: Danish

1043: Dutch

1035: Finnish

1036: French

1031: German

1040: Italian

1041: Japanese

1042: Korean

1044: Norwegian

1034: Spanish

1053: Swedish

1049: Russian

1045: Polish

14337: Arabic

1029: Czech

1032: Greek

1037: Hebrew

1050: Croatian

1038: Hungarian

2070: Portuguese (European)

1048: Romanian

1055: Turkish

/ru - Suppress reboot at the end of uninstall. (Relevant for Windows 98 and ME during upgrade)

/ri - Suppress reboot at the end of install (Relevant for Windows 98 and ME and if reboot is required on Windows 2000).

For example, to install silently without any UI in German language, use the following command line

setup.exe /qn /L1031

## Signed Driver Report

Folder: w:\BTW\btw1.2\bin\drivers

Driver: Signed? Signature: Valid? SubmissionID: Version:

Driver	Signed?	Signature	Valid?	SubmissionID	Version
btaudio.cat	Yes	WHQL	Yes	1293810	5.5.0.3500
btfaxmdm.cat	Yes	WHQL	Yes	1283216	5.5.0.2300
btport.cat	Yes	WHQL	Yes	1283221	5.5.0.2300
btusbflt.cat	Yes	WHQL	Yes	1280598	6.2.0.1300
btw.cat	Yes	WHQL	Yes	1310707	5.5.0.5200
btwdndis.cat	Yes	WHQL	Yes	1300680	5.5.0.4000
btwhidnt.cat	Yes	WHQL	Yes	1284132	5.5.0.2600
btwacm.cat	Yes	WHQL	Yes	1283232	5.5.0.2300
btwusb.cat	Yes	WHQL	Yes	1313973	5.5.0.5700
frmupgr.cat	Yes	WHQL	Yes	1280599	6.2.0.1300
wc_modem.cat	Yes	WHQL	Yes	1283226	5.5.0.2300
bcbthid32.cat	Yes	WHQL	Yes	1286483	6.1.0.4500

Folder: w:\BTW\btw1.2\bin\amd64\drivers

Driver: Signed? Signature: Valid? SubmissionID: Version:

Driver	Signed?	Signature	Valid?	SubmissionID	Version
btaudio.cat	Yes	WHQL	Yes	1293810	5.5.0.3500
btfaxmdm.cat	Yes	WHQL	Yes	1283216	5.5.0.2300
btport.cat	Yes	WHQL	Yes	1283221	5.5.0.2300
btusbflt64.cat	Yes	WHQL	Yes	1280598	6.2.0.1300
btw.cat	Yes	WHQL	Yes	1310707	5.5.0.5200
btwdndis.cat	Yes	WHQL	Yes	1300680	5.5.0.4000
btwhidnt.cat	Yes	WHQL	Yes	1284132	5.5.0.2600
btwacm.cat	Yes	WHQL	Yes	1283232	5.5.0.2300
btwusb.cat	Yes	WHQL	Yes	1313973	5.5.0.5700
frmupgr64.cat	Yes	WHQL	Yes	1280599	6.2.0.1300
wc_modem.cat	Yes	WHQL	Yes	1283226	5.5.0.2300
bcbthid64.cat	Yes	WHQL	Yes	1286483	6.1.0.4500

# BTW 5.5.0.5800

---

## Resolved Defects

---

Major

---

**BLTH00148828**

**Subsystem:** Unknown

**Headline:**

Japanese: Client Application tab: Bluetooth Imaging and Human Device Interface strings not localized.

**Release Note:**

Japanese: Client Application tab: Bluetooth Imaging and Human Device Interface strings is localized.

---

---

**BLTH00152630**

**Subsystem:** Localization

**Headline:**

Simplified Chinese : BTW shows services in English during setup.

**Release Note:**

Fixed installer issue

---

---

**BLTH00154555**

**Subsystem:** Documentation

**Headline:**

BTW5.5 – Check in new help files provided by tech pub folks

**Release Note:**

Checked in all the help fixes into the build

---

## BTW 5.5.0.5800

---

### Resolved Defects

---

Minor

**BLTH00154389**

**Subsystem:** Other

**Headline:**

BTW uses OPP instead of BIP for printing image on printer Epson Stylus Photo RX595

**Release Note:**

Defect is fixed when BTW uses OPP instead of BIP for printing image on printer Epson Stylus Photo RX595

BTW did not use BIP if printer does not support ImagePush feature. RX595 does not support ImagePush but supports ImagePush\_Print.

---

**BLTH00154413**

**Subsystem:** Other

**Headline:**

Pairing wizard should not show service selection page if it is started for pin code request during SendTo

**Release Note:**

Defect is fixed when Pairing wizard shows service selection page if it is started for pin code request during SendTo. It should just exit after pairing in such case.

---

---

### Resolved Defects

---

Enhancements

**BLTH00154200**

**Subsystem:** EasyConnect

**Headline:**

EasyConnect manifest change for OEM Ready

**Release Note:**

Added required trustInfo section to manifest

---